

T.I. no.: 2025-01 Updated: -	Topic: Software version 3.0.6
---	--------------------------------------

Date: 1/27/2025	Priority and need for action	
Affected machines: BARISTA	<input type="checkbox"/> High: as soon as possible	
From serial number: yywwXXXXXX	<input checked="" type="checkbox"/> Medium: next visit	<input type="checkbox"/> Medium: change in stock
From date: right away	<input type="checkbox"/> Low: FYI only	

INFORMATION ON SOFTWARE VERSION 3.0.6

Compared to software version 3.0.4, the transmission of extraction times by telemetry has been optimized in software version 3.0.6.

DESCRIPTION AND SOLUTION OF PROBLEM

With software version 3.0.4, the extraction times of the brewing group on the right were not transmitted to Coffee Connect by telemetry. This malfunction was fixed in the new software version 3.0.6.

Tested update scenarios

The following update tests were successfully carried out as part of the approval test:

Machine	From version	To version
Schaerer Barista: all variants	V2.6.2, V3.0.4	V3.0.6

Update of performance level versions:

When error **9883** appears during an update, the firmware update of the performance level must be carried out manually.

Call-up

[Service](#) > [Service routines](#) > [Firmware update performance levels](#)

Software simulator:

Nothing has changed for the software simulator resulting from the optimization described above. That means the simulator from 3.0.4 can continue to be used.

	NOTE FOR TECHNICIANS
	Problems during or after the software update
	<p>If problems occur during or after the software update:</p> <p>Please send a data backup together with an exact description of the error in an e-mail to the contact address below.</p>

Service contact

Global Technical Support Team
 GBU Professional Coffee Machines

- > Support hotline: +41 32 681 62 75 (10:00-11:30 a.m. CET/3:00-4:30 p.m. CET)
- > Support e-mail: technical-support@schaerer.com